

# UUMAX3 - UMAP Termination Exit

UUMAX3 is a user-written routine called by the UMAP utility program before exiting UMAP. This module allows you to force cleanup of SD files, and to control the termination of UMAP.

This chapter covers the following topics:

- How to Use UUMAX3
  - UUMAX3 Conventions
- 

## How to Use UUMAX3

Upon entry to UUMAX3, a set of parameters is received in the form of fullword addresses pointed to by register 1.

## UUMAX3 Conventions

The following table summarizes the linkage conventions of UUMAX3.

Feature	Convention
Attributes	None required.
Type	Thread.
Size	Restricted to the UMAP thread region
Registers at Entry	<p>Register 1      Address of the parameter list</p> <p>Register 13     Address of an 18-fullword save area</p> <p>Register 14     Return address in the calling module</p> <p>Register 15     Entry address of UUMAX3</p>
Registers at Return	Registers 2 through 13 remain unchanged. Register 15 is ignored.
Parameters	<p>Word 1      Address of the eight-byte user ID.</p> <p>Word 2      Address of the two-byte TID.</p> <p>Word 3      List of the five eight-byte SD file name fields. If less than five names are in the list, the list of valid names will be terminated with a HEX '00'.</p> <p>Word 4      Address of the eight-byte user exit communications area. This area is passed to all user exits and is neither modified nor accessed by UMAP.</p>
Return Codes	Ignored.
Considerations	Can be link edited, or loaded dynamically.